Soft Phone connection

Set up a software telephone so that you can play with Voximal. We recommend Zoiper or YateClient which are free. Download them from :

- IaxLite (old windows application)
- Zoiper (freeware with commercial offer)
- YateClient (opensource freeware)

Account datas :

- username : user
- password : (get it form the Voximal/Settings/Test)
- server : (the IP adress of your server)

Get your password from the Web Interface

Select Setting → Voximal Setting → Test



Get your password from the Asterisk console

Execute :

```
raspbx*CLI> voximal show license
Version       : V14.0
Build
 CVS Revision : $Revision: 1.853 $
```

```
 Gcc           : V4.9
 Arch          : 32 bits
 Target        : i686
 Asterisk      : V13.11.2
 Options sum   :
 Date          : Nov  3 2016 21:40:06
Code           : b6de76bcb827eb415eb3b6f75b1001
UID            : cb773b52-a362-11e6-af57-b827eb415eb3
PIN            : 3152
Password       : cb773b52
Key            :
Max sessions   : 1
Options
 TextToSpeech  : Yes
 Speech        : Yes
State          : ok
```

Your password is : **cb773b52**

IaxLite

- Run IAXLite once you've installed it and enter the credentials for the account on your Voximal. You'll need the IP address of your server and your extension 'user' password.
- Click the **[Set.]** button.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.



Zoiper

- Run Zoiper once you've installed it and enter the credentials for the account on your Voximal. You'll need the IP address of your server and your extension 'user' password.

- Choose Settings → Accounts and click the **[Create Account]** button.
- Select IAX.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.



YateClient

- Run YateClient once you've installed it and enter the credentials for the 'user' extension on Voximal. You'll need the IP address of your server plus your extension user password.

- Choose Settings → Accounts and click the **[New]** button.
- Fill in the blanks using the IP address of your server, 'user' for your account name, and whatever password got from your Voximal installation server.



From:
https://wiki.voximal.com/ - **Voximal documentation**

Permanent link:
https://wiki.voximal.com/doku.php?id=installation_guide:softphone:start

Last update: **2018/05/07 11:26**